MacOS 7.6 through 8.1 Internet Setup

*Connection instructions for the Macintosh **Internet Setup Assistant***

Step 1: *Getting Started*

Double-click on the 

icon. Then double-click to open the 

folder. You will then see an icon for
double-click on this icon.

Internet Setup Assistant

Step 2: *Creating a Profile*

These steps will guide you though creating a profile that will connect you to Spacestar. Follow these few steps, and you will be online sending mail, surfing the internet, and chatting with friends



Click on the "**Update**" to add a new profile.



Step 3: *Introduction*

Next, you will then see a welcome screen that explains the services you are setting up. Click on the right arrow at the bottom to continue.

Step 4: *Gathering Information*



Here is the beginning of the setup process. Select **"Add Internet Configuration"** and click on the right arrow to continue.

Step 5: *Connection Type*

Here is where the connection profile is named. In the box where it asks, **"What would you like to name this configuration?"** Enter in the name **Spacestar**.

Under the section where it asks, **"How will you be connecting to the Internet?"** Select the button next to **Modem**. When you are finished, click on the right arrow to continue.





Step 6: *Selecting Your Modem*

Select the kind of modem you are using from the list. If you cannot find your modem, select the **3Com Impact Analog 14.4** modem.

"Modem Port" or **"Internal Modem"** is normally set for the Port. Some laptops may have an option for **Upper or Lower Card Slot**.

Click on the right arrow to continue.

Step 7: *User Information*



Here is where your dialup information is entered. The first box asks you for the Spacestar Dialup number. Type in the appropriate number from the **Internet Setup Information** sheet provided.

Step 8: *IP Addressing*

This screen asks if you are using a Static IP. Most users **do not** have one. Select '**No**' and click on the right arrow to continue.

Step 9: *Domain Name Servers*



Domain Name Servers are necessary for connecting your computer to the Internet. In the larger box, type in the following sets of numbers:

206.191.193.1
206.191.193.2

In the second box, type in **spacestar.net** and then click on the right arrow to continue.

Step 10: *Setting up E-Mail*

This is where your mail account information is entered.

Type your e-mail address in the upper box.

Next, enter your password in the lower box.

Click on the right arrow to continue.



This is where your mail account information is entered.

In the top box, type in your POP account using the following form:

username@pop3.spacestar.net

In the bottom box, type in:

smtp.spacestar.net

Step 12: *Setting up the News Server*

Here, the setup program is looking for a newsgroup server. In this box, type in the following news server address:

news.spacestar.net

Step 13: *Finished*

Congratulations! You're finished!

If **"Connect when finished"** is selected, then the program will open up the **PPP** program when you click on **Go Ahead**.

PPP (point-to-point protocol) is the program that is used to dial up into the Spacestar Internet Service.

If you need basic startup software, more setup information, or have having trouble logging on, please contact us.

Local Dial up number- Choose from the following list for the appropriate number:

Twin Cities	612.252.1000	Thief River Falls	218.681.6886
Afton	651.436.1000	Virginia	218.741.8875
St. Cloud	320.257.1000	Crookston	218.281.6161
Duluth	218.722.5179	Annandale / Maple Lake	320.963.5686
Bemidji	218.751.6129	Hudson	715.386.6500
Aurora	218.229.3320	River Falls	715.426.2200
Cook / Orr	218.666.5994	Spooner	715.635.8925
Ely	218.365.7078	Amery	715.268.5330
Grand Rapids	218.327.2466	Fargo	701.232.1690
St. Croix Electric	715796.5661	Willmar	320.231.2837

Office Hours

Main office:	8:00am to 5:00pm	(M-F)
Sales:	8:00am to 5:00pm	(M-F)
Billing:	8:00am to 4:30pm	(M-F)
Technical Support:	24 hours	(M-F)
	12:00am to 11:00pm	(Sat)
	8:00am to 11:00pm	(Sun)

Telephone Numbers

Twin Cities	612.996.0000
Hudson / River Falls	715.426.2236
Houlton	715.386.5622
Willmar	320.231.8342
Maple Lake	320.963.3854
All Other Areas	800.772.0896

E-Mail

Sales	sales@spacestar.net
Billing	billing@spacestar.net
Technical Support	support@spacestar.net